

!A

*** End of Pass 1

*** End of Pass 2

```
0800          1          ttl "SOURCEROR Loader Source Code, LOADSRCRR.L"
0800          2          ;
0800          3          ;
0800          4          ; LOADSRCRR.L
0800          5          ;
0800          6          ;
0800          7          ; SOURCEROR Loader Source Code
0800          8          ;
0800          9          ; 2024 February 14
0800         10          ;
0800         11          ;
0800         12          ; DOS 4.5, Build 06
0800         13          ;
0800         14          ; 2024 February 14
0800         15          ;
0800         16          ;
0800         17          ; Start of Source Code: 0x4000
0800         18          ; Start of Symbol List: 0x7800
0800         19          ;
0800         20          ;
0800         21          ; Copyright (c) 2024 February 14 by
0800         22          ; Walland Philip Vrbancic Jr
0800         23          ;
0800         24          ; 6223 East Peabody Street
0800         25          ; Long Beach, California 90808
0800         26          ; Unitied States of America
0800         27          ;
0800         28          ; All Rights Reserved
0800         29          ;
0800         30          ; This software is the confidential and
0800         31          ; proprietary intellectual property of
0800         32          ; Walland Philip Vrbancic Jr
0800         33          ;
0800         34          ;
0800         35          enz
0800         36          ;
0000         37          ZERO      equ $00
0084         38          CTRLD     equ $84
008D         39          RETURN    equ $8D
0800         40          ;
03EA         41          HOOKDOS   equ $3EA
0800         42          ;
AC00         43          START     equ $AC00
0800         44          ;
FDED         45          COUT      equ $FDED
0800         46          ;
0800         47          ;
0300         48          org $300
0300         49          obj $300
0300         50          usr
0300         51          ;
0300         52          ;
0300 20 EA 03   53          jsr HOOKDOS
0303         54          ;
0303 A0 00     55          ldy #ZERO
0305         56          ;
0305 B9 13 03  57          ^1     lda MSG,Y
0308 F0 06     58          beq >2
030A         59          ;
030A 20 ED FD  60          jsr COUT
```

```
030D          61 ;
030D C8        62      iny
030E D0 F5     63      bne <1
0310          64 ;
0310 4C 00 AC   65 ^2      jmp START
0313          66 ;
0313          67 ;
0313 8D 84     68 MSG      byt RETURN,CTRLD
0315 C2 CC CF   69      asc "BLOAD SOURCEROR,A$AC00"
0318 C1 C4 A0
031B D3 CF D5
031E D2 C3 C5
0321 D2 CF D2
0324 AC C1 A4
0327 C1 C3 B0
032A B0
032B 8D 00     70      byt RETURN,ZERO
032D          71 ;
032D          72 ;
```

BSAVE LOADSRCRR,A\$0300,B,L\$002D

```
032D          73      usr LOADSRCRR
032D          74 ;
032D          75 ;
032D          76      stt "LOADSRCRR Symbol Table"
032D          77 ;
032D          78 ;
032D          79      end 111
```

*** End of Assembly

Symbol List starts at 0x7800, ends at 0x785A, used 0x005A, remaining 0x3F4E

Symbols unsorted:

ZERO	0000	CTRLD	0084	RETURN	008D	HOOKDOS	03EA	START	AC00
COUT	FDED	MESG	0313						

Symbols alphabetically sorted:

COUT	FDED	CTRLD	0084	HOOKDOS	03EA	MESG	0313	RETURN	008D
START	AC00	ZERO	0000						

Symbols numerically sorted:

ZERO	0000	CTRLD	0084	RETURN	008D	MESG	0313	HOOKDOS	03EA
START	AC00	COUT	FDED						