

m

!p0

!A

*** End of Pass 1

*** End of Pass 2

```
0800          1          ttl "test, TEST.L"
0800          2          ;
0800          3          ;
0800          4          ; TEST.L
0800          5          ;
0800          6          ;
004C          7  DOSPTR    epz  $4C
0800          8          ;
0000          9  ZERO      equ  $00
0800         10          ;
0100         11  STACK     equ  $100
0800         12          ;
03E1         13  RDCLKVSN  equ  $3E1
03EA         14  HOOKDOS   equ  $3EA
0800         15          ;
0800         16          ;
0300         17          org  $300
0300         18          obj  $300
0300         19          usr
0300         20          ;
0300         21          ;
0300 A5 4C     22          lda  DOSPTR
0302 8D 28 03  23          sta  BUFFER
0305         24          ;
0305 A5 4D     25          lda  DOSPTR+1
0307 8D 29 03  26          sta  BUFFER+1
030A         27          ;
030A A0 10     28          ld  y #STACK+$10
030C A9 01     29          lda  /STACK+$10
030E         30          ;
030E 20 1C 03  31          jsr  RDCLOCK
0311         32          ;
0311 AD 28 03  33          lda  BUFFER
0314 85 4C     34          sta  DOSPTR
0316         35          ;
0316 AD 29 03  36          lda  BUFFER+1
0319 85 4D     37          sta  DOSPTR+1
031B         38          ;
031B 60        39          rts
031C         40          ;
031C         41          ;
031C 18        42  RDCLOCK  clc
031D         43          ;
031D 6C E1 03  44          jmp  (RDCLKVSN)
0320         45          ;
0320         46          ;
0320         47          dfs  $328-*,ZERO
0328         48          ;
0328         49          ;
0328         50  BUFFER    dfs  32,ZERO
0348         51          ;
0348         52          ;
```

BSAVE TEST,A\$0300,B,L\$0048

```
0348         53          usr  TEST
0348         54          ;
0348         55          ;
0348         56          end 111
```

*** End of Assembly

Symbol List starts at 0x7800, ends at 0x785A, used 0x005A, remaining 0x3FA6

Symbols unsorted:

DOSPTR	004C	ZERO	0000	STACK	0100	RDCLKVSN	03E1	HOOKDOS	03EA
RDCLOCK	031C	BUFFER	0328						

Symbols alphabetically sorted:

BUFFER	0328	DOSPTR	004C	HOOKDOS	03EA	RDCLKVSN	03E1	RDCLOCK	031C
STACK	0100	ZERO	0000						

Symbols numerically sorted:

ZERO	0000	DOSPTR	004C	STACK	0100	RDCLOCK	031C	BUFFER	0328
RDCLKVSN	03E1	HOOKDOS	03EA						